



**FortiGate Support for SCCP  
FortiOS v3.0 MR6**



[www.fortinet.com](http://www.fortinet.com)

*FortiGate SCCP Technical Note*  
FortiOS v3.0 MR6  
25 April, 2008  
01-30006-0467-20080425

© Copyright 2008 Fortinet, Inc. All rights reserved. No part of this publication including text, examples, diagrams or illustrations may be reproduced, transmitted, or translated in any form or by any means, electronic, mechanical, manual, optical or otherwise, for any purpose, without prior written permission of Fortinet, Inc.

**Trademarks**

Dynamic Threat Prevention System (DTPS), APSecure, FortiASIC, FortiBIOS, FortiBridge, FortiClient, FortiGate, FortiGate Unified Threat Management System, FortiGuard, FortiGuard-Antispam, FortiGuard-Antivirus, FortiGuard-Intrusion, FortiGuard-Web, FortiLog, FortiAnalyzer, FortiManager, Fortinet, FortiOS, FortiPartner, FortiProtect, FortiReporter, FortiResponse, FortiShield, FortiVoIP, and FortiWiFi are trademarks of Fortinet, Inc. in the United States and/or other countries. The names of actual companies and products mentioned herein may be the trademarks of their respective owners.

# FortiGate Support for SCCP

The Skinny Client Control Protocol (SCCP) protocol is used for establishing and conducting multi-media calls over TCP/IP networks. Due to the complexity of the call setup, not every firewall can handle SCCP calls correctly, even if the firewall is stateful. The FortiGate Antivirus Firewall includes special module that tracks SCCP calls. The FortiGate unit can make all necessary adjustments, to both the firewall state and call data, to ensure a seamless call is established through the FortiGate unit regardless of its operation mode, NAT, route, or transparent.

This technical note describes SCCP scenarios supported by FortiGate units. The scenarios are broken down into two groups: direct calls and gatekeeper-routed calls.



**Note:** Signaling and media information are transmitted in separate IP flows, so a media gateway, signaling gateway or media gateway controller (softswitch) are between the terminals. They may be separate physical devices or integrated in any combination. For simplicity, these devices are not shown and described in this document.

## Configuring SCCP settings

You can configure SCCP rate limiting and logging by creating a firewall protection profile. Rate limiting enables you to control call setup rate. Logging allows you to track information available in the statistical summary.

### To configure SCCP settings

- 1 Go to **Firewall > Protection Profile**.
- 2 Select create New.
- 3 Enter SCCP\_protection for Profile Name.
- 4 Select the blue arrow to expand the VoIP options.
- 5 Select the SCCP checkbox.
- 6 Enter a value for call setups per minute in the Limit Call Setup (Calls/min/client) field.
- 7 Select the blue arrow to expand the Logging options.
- 8 Select Log VoIP Activity.
- 9 Select OK.

### To view SCCP statistics

- 1 Go to **IM, P2P & VoIP > Statistics > Summary**.
- 2 Go to the **VoIP Usage** section.

Sessions		
	<b>Active Sessions (phones connected)</b>	Number of sessions that are currently active.
Voice Calls		
	<b>Total calls (since last reset)</b>	Total VoIP calls since the last FortiGate unit reset.
	<b>Calls failed/Dropped</b>	Number of VoIP sessions that failed during the reporting period.
	<b>Calls Succeeded</b>	Number of VoIP sessions that were successfully completed during the reporting session.



**Note:** : If virtual domains are enabled on the FortiGate unit, IM, P2P and VoIP features are configured globally.

## Direct SCCP Calls

Direct SCCP traffic passes from terminal to terminal through a FortiGate unit. Policies are created on the FortiGate unit to allow SCCP traffic to pass through in either direction. NAT may or may not be applied.

A single firewall policy is required for a terminal on the internal network to initiate connections with terminals on the external network. When a terminal initiates a call, two-way communication is allowed because rules are automatically created based on data found in the call setup messages. A virtual IP address may be required if traffic is coming from an external public network to the internal private network.

### Scenario 1: FortiGate unit in Transparent mode

Figure 1: FortiGate unit in Transparent mode



The FortiGate unit is operating in Transparent mode. NAT is not available or required in Transparent mode because all FortiGate interfaces are on the same network.

The following firewall policies are required:

- internal -> external to allow Terminal A to initiate connections with Terminal B. Set service to SCCP.
- external -> internal to allow Terminal B to initiate connections with Terminal A. Set service to SCCP.

## Scenario 2: FortiGate unit in NAT/Route mode, NAT not enabled

Figure 2: FortiGate unit in NAT/Route mode



The FortiGate unit is operating in NAT/Route mode without NAT being enabled.

The following policies are required:

- internal -> external to allow Terminal A to initiate connections with Terminal B. Set service to SCCP.
- external -> internal to allow Terminal B to initiate connections with Terminal A. Set service to SCCP.

## Scenario 3: FortiGate unit in NAT/Route mode, NAT enabled and virtual IP required

Figure 3: FortiGate unit in NAT/Route mode



The FortiGate unit is operating in NAT/route mode with NAT enabled. For Terminal A to be able to call Terminal B, you require the following:

- an internal -> external policy to allow Terminal A to initiate connections with Terminal B. Enable NAT. Set service to SCCP

For Terminal B to be able to call Terminal A, you require the following:

- a virtual IP on the internal interface
- an external -> internal policy to allow Terminal B to initiate connections with Terminal A. Set the destination address to the virtual IP address. Set service to SCCP.

## Gatekeeper-routed Calls

A gatekeeper is an optional component that acts as a call manager. Services provided by gatekeepers include

- translation of alias addresses for terminals and gateways to transport addresses
- bandwidth management
- authorization and authentication
- call signalling
- call routing

- call management


A gatekeeper may be located on the terminal network or outside of the terminal network. A gatekeeper may include a multipoint control unit (MCU) to provide conferencing between three or more terminals.

With gatekeeper-routed calls, a terminal registers with the gatekeeper when it is powered up. When the terminal places a call, the gatekeeper contacts the destination terminal and relays data between the terminals. The terminals complete call setup.

A single firewall policy is required for a terminal on the internal network to initiate connections with the gatekeeper on the external network. When a terminal initiates a call, two-way communication is allowed because rules are automatically created based on data found in the call setup messages.

### Gatekeeper scenario 1: FortiGate unit in Transparent mode

Figure 4: FortiGate unit in Transparent mode




The FortiGate unit is operating in Transparent mode. NAT is not available or required in Transparent mode because all FortiGate interfaces are on the same network.

The following firewall policy is required:

- internal -> external to allow Terminals A and C to connect to the gatekeeper. Set service to SCCP.

## Gatekeeper scenario 2: FortiGate unit in NAT/Route mode, NAT not enabled

Figure 5: FortiGate unit in NAT/route mode




The FortiGate unit is operating in NAT/Route mode with NAT not enabled

The following policy is required:

- internal -> external to allow Terminals A and C to connect to the gatekeeper. Set service to SCCP.

## Gatekeeper scenario 3: FortiGate unit in NAT/Route mode, NAT enabled and virtual IP required

Figure 6: Gatekeeper on the private network




The FortiGate unit is operating in NAT/Route mode with NAT enabled.

For Terminal B to be able to register with the gatekeeper, you require the following:

- a virtual IP for the gatekeeper on the external interface.
- an external -> internal policy to allow Terminal B to initiate connections with the gatekeeper. Set the destination address to the virtual IP address. Set service to SCCP.

### Gatekeeper scenario 4: FortiGate unit in NAT/Route mode, NAT enabled

Figure 7: Gatekeeper on the public network




The FortiGate unit is operating in NAT/Route mode with NAT enabled.

The following policy is required:

- internal -> external to allow Terminals A and C to connect to the gatekeeper. Set service to SCCP.

### Gatekeeper scenario 5: FortiGate unit in NAT/Route mode, NAT enabled

Figure 8: Gatekeeper on a different network




The FortiGate unit is operating in NAT/Route mode with NAT enabled.

The following policies are required:

- internal -> DMZ to allow Terminals A and C to connect to the gatekeeper. Set service to SCCP.
- external -> DMZ to allow Terminal B to connect to the gatekeeper.

## Example Configuration 1: Direct SCCP Calls

This example shows how to configure a policy for direct SCCP connections. The FortiGate unit is in NAT/Route mode.



This configuration has two basic steps:

- configure addresses for the internal terminal (terminal\_A) and external terminal (terminal\_B)
- configure a firewall policy for SCCP traffic between the terminals (internal -> external)

### To add terminal addresses

- 1 Go to **Firewall > Address** and select Create New.
- 2 Configure the address as follows:

<b>Address Name</b>	terminal_A
<b>Subnet/IP Range</b>	255.255.255.0/192.168.33.1

- 3 Select OK.
- 4 Repeat steps 2 and 3 for terminal\_B:

<b>Address Name</b>	terminal_B
<b>Subnet/IP Range</b>	255.255.255.0/172.20.33.1

### To add a firewall policy

- 1 Go to **Firewall > Policy** and select Create New.
- 2 Configure the policy as follows:

<b>Source Interface/Zone</b>	internal
<b>Source Address</b>	terminal_A
<b>Destination Interface/Zone</b>	external
<b>Destination Address</b>	terminal_B
<b>Schedule</b>	always
<b>Service</b>	SCCP
<b>Action</b>	ACCEPT
<b>NAT</b>	enable

- 3 Select OK.

## Example Configuration 2: Direct SCCP Calls with a Virtual IP Address

This example shows how to configure a policy for direct SCCP connections.



### To add terminal addresses

- 1 Go to **Firewall > Address** and select Create New.
- 2 Configure the address as follows:

<b>Address Name</b>	terminal_A
<b>Subnet/IP Range</b>	255.255.255.0/192.168.33.1

- 3 Select OK.
- 4 Repeat steps 2 and 3 for terminal\_B:

<b>Address Name</b>	terminal_B
<b>Subnet/IP Range</b>	255.255.255.0/172.20.33.1

### To add a firewall policy

- 1 Go to **Firewall > Policy** and select Create New.
- 2 Configure the policy as follows:

<b>Source Interface/Zone</b>	internal
<b>Source Address</b>	terminal_A
<b>Destination Interface/Zone</b>	external
<b>Destination Address</b>	terminal_B
<b>Schedule</b>	always
<b>Service</b>	SCCP
<b>Action</b>	ACCEPT
<b>NAT</b>	enable

- 3 Select OK.

### To configure a virtual IP address

- 1 Go to **Firewall > Virtual IP** and select Create New.
- 2 Configure the virtual IP address as follows:

<b>Name</b>	terminal_A_vip
<b>External Interface</b>	external
<b>Type</b>	Static NAT
<b>External IP Address/Range</b>	172.20.32.25
<b>Mapped IP Address/Range</b>	192.168.33.1/255.255.255.0

- 3 Select OK.

### To add an external to internal firewall policy


- 1 Go to **Firewall > Policy** and select Create New.
- 2 Configure the policy as follows:

<b>Source Interface/Zone</b>	external
<b>Source Address</b>	terminal_B
<b>Destination Interface/Zone</b>	internal
<b>Destination Address</b>	terminal_A_vip
<b>Schedule</b>	always
<b>Service</b>	SCCP
<b>Action</b>	ACCEPT
<b>NAT</b>	enable

- 3 Select OK.

## Example Configuration 3: Gatekeeper

This example shows how to configure a policy for SCCP connections using a gatekeeper. The FortiGate unit is in NAT/Route mode.



This configuration has three basic steps:

- configure addresses for the internal terminals (terminal\_A and terminal\_C) and external terminal (terminal\_B)
- create groups for the terminals (internal\_terminals)
- configure a firewall policy for SCCP traffic between the terminals and the gatekeeper (internal -> external)

### To add terminal addresses

- 1 Go to **Firewall > Address** and select Create New.
- 2 Configure the address as follows:

<b>Address Name</b>	terminal_A
<b>Subnet/IP Range</b>	255.255.255.0/192.168.33.1

- 3 Select OK.
- 4 Repeat steps 2 and 3 for terminal\_C and the gatekeeper:

<b>Address Name</b>	terminal_C
<b>Subnet/IP Range</b>	255.255.255.0/192.168.33.2
<b>Address Name</b>	gatekeeper
<b>Subnet/IP Range</b>	255.255.255.0/172.50.23.10

**To add address groups**

- 1 Go to **Firewall > Address > Group** and select Create New.
- 2 Enter the Group Name: internal\_terminals.
- 3 Using the right arrow, move terminal\_A and terminal\_C from the Available Addresses list to the Members list.
- 4 Select OK.

**To add a firewall policy**

- 1 Go to **Firewall > Policy** and select Create New.
- 2 Configure the policy as follows:.

<b>Source Interface/Zone</b>	internal
<b>Source Address</b>	internal_terminals
<b>Destination Interface/Zone</b>	external
<b>Destination Address</b>	gatekeeper
<b>Schedule</b>	always
<b>Service</b>	SCCP
<b>Action</b>	ACCEPT
<b>NAT</b>	enable

- 3 Select OK.

